
Gio Vase, Raspberry-radio

Release 1.8

Author: Monica Amico

Jun 29, 2020

CONTENTS:

1	Constant	1
2	Request	3
3	Threads	5
	Python Module Index	7
	Index	9

CONSTANT

class constants.**Operation** (*value*)

Type of Operation Enum

- JOINED = 0
- REFUSED = 1
- PING = 2
- HUMIDITY = 3
- TEMPERATURE = 4
- LIGHT = 5
- WATER = 6
- SET_HUMIDITY_MIN = 7
- SET_HUMIDITY_MAX = 8
- SET_TEMPERATURE_MIN = 9
- SET_TEMPERATURE_MAX = 10
- SET_LIGHT_MAX = 11
- SET_LIGHT_MIN = 12
- SET_VASE_PAUSE_TIME = 13
- SET_VASE_SEND_TIME = 14
- SET_RADIO_PAUSE_TIME = 15
- SET_RADIO_DIED_PING = 16
- CONNECTION = 17
- DELETED = 18
- SET_WATERING_LIGHT = 19
- SET_WATER_CONTAINER_SIZE = 20
- WATER_CONTAINER_STATE = 21
- RADIO_JOIN = 22
- RADIO_TRANSMIT_POWER = 23
- VASE_TRANSMIT_POWER = 24
- ADD_EXISTING_VASE = 26

```
class constants.WaterContainerState (value)  
    Water container state enum - Empty = 0 - Full = 1
```

REQUEST

`request.request()`

Reads the received request from the dashobard server and adds that to the request queue.

THREADS

class threads.**Reader** (*nome*)
Thread Reader

run ()
Method representing the thread's activity.
It calls the function *reader()*

class threads.**Writer** (*nome*)
Thread Writer

run ()
Method representing the thread's activity.
It calls the function *writer()*

threads.**read_serial** ()
Read a row from the serial port.

Returns request, serial number, signal, param

Return type str

threads.**reader** ()
Called from the Thread Reader, to read request/response from radio-microbit. if the request/response received is valid send it to the dashboard, throw HTTP request.

threads.**write_serial** (*data*)
Writes data in the serial port.

Parameters *data* (*str*) – data to be written in the serial port

Returns len(*data*)

Return type int

threads.**writer** ()
Called from the Thread Writer, to take the requests from the queue (dashboard's requests) and to send them to the microbit, writing the data of the requests into the serial port.

PYTHON MODULE INDEX

c

constants, [1](#)

r

request, [3](#)

t

threads, [5](#)

INDEX

C

constants
 module, 1

M

module
 constants, 1
 request, 3
 threads, 5

O

Operation (*class in constants*), 1

R

read_serial() (*in module threads*), 5
Reader (*class in threads*), 5
reader() (*in module threads*), 5
request
 module, 3
request() (*in module request*), 3
run() (*threads.Reader method*), 5
run() (*threads.Writer method*), 5

T

threads
 module, 5

W

WaterContainerState (*class in constants*), 1
write_serial() (*in module threads*), 5
Writer (*class in threads*), 5
writer() (*in module threads*), 5